
NOTE TO USERS

CompactRIO™ cRIO-9014

Installing LabVIEW and NI-RIO Software on the cRIO-9014

You cannot install software to the cRIO-9014 controller using Measurement & Automation Explorer (MAX) unless you have LabVIEW Real-Time 8.2.1 or later installed on the host computer. If you need to reinstall software on the cRIO-9014 controller, you can format the disk on the controller and FTP the contents of the 9014 folder on the second NI-RIO Software CD to the controller. For more information, please refer to ni.com/info and enter the info code MAX9014 for more information.

National Instruments, NI, ni.com, and LabVIEW are trademarks of National Instruments Corporation. Refer to the *Terms of Use* section on ni.com/legal for more information about National Instruments trademarks. Other product and company names mentioned herein are trademarks or trade names of their respective companies. For patents covering National Instruments products, refer to the appropriate location: **Help»Patents** in your software, the `patents.txt` file on your CD, or ni.com/patents.