

## FPAttributeValueFile

0 GetIntAttr 1 2 false g

1 all "Input buffer length" ATTR\_INPUT\_BUFFER\_LEN i g  
"Input buffer length"

1 all "Output buffer length" ATTR\_OUTPUT\_BUFFER\_LEN i g  
"Output buffer length"

1 all "Input Overflow" ATTR\_INPUT\_OVEFLOW i g  
"Input overflow"

1 all "Output Overflow" ATTR\_OUTPUT\_OVEFLOW i g  
"Output overflow"

0 GetFloatAttr 1 2 false g

1 all "Input buffer timeout" ATTR\_INPUT\_BUFFER\_TIMEOUT float g  
"Input buffer timeout"

1 all "Output buffer timeout" ATTR\_OUTPUT\_BUFFER\_TIMEOUT float g  
"Output buffer timeout"

1 all "Input buffer fill percentage" ATTR\_INPUT\_BUFFER\_FILL float g  
"Input buffer full rate in percent"

1 all "Output buffer fill percentage" ATTR\_OUTPUT\_BUFFER\_FILL float g  
"Output buffer full rate in percent"